

Sound sets in Sibelius 3

For advanced users only!

Sibelius 3 includes a sound set editor within the main application (see **Edit Sound Sets** in the Sibelius 3 User Guide for details). The sound set editor should fulfill most user needs. This document may be useful to users who need to do batch processing on sound set files, or who need to generate sound sets automatically. You can also assign any patch to more than one group if you edit a sound set file directly – the sound set editor in Sibelius 3 will not let you do this (see below for details).

Before attempting to create your own sound set, it is worth checking if one is already available: see the online Help Center at <http://www.sibelius.com/helpcenter/resources/> for the latest additions.

Disclaimer

Sound sets are complex files and are not designed to be user-editable. Using a sound set with incorrect syntax may cause your copy of Sibelius to behave unpredictably or even crash. Sibelius Software accepts no responsibility for any loss of data or other problems experienced as a result of editing the supplied sound sets or creating new ones. This document is provided "as is," and no warranty, implied or otherwise, covers the information contained within.

Please also note that we do not offer technical support on the editing or creation of sound set files.

Filenames

The filename of a sound set file is insignificant (i.e. it is not shown in the **Play ▶ Devices** dialog), but we recommend that it should be fairly descriptive. It should also be 31 characters or less (including the **.set** file extension) to ensure compatibility with all file systems.

File format

In Sibelius 3 sound set files can either be in a text or binary format. The binary format is more compact and much quicker to load. All the sounds sets installed with Sibelius are in the binary format. Only the text format is described in this document. To convert from text to binary format you can use the sound set editor within Sibelius (see the Sibelius 3 User Guide for details).

Example sound set

In order to understand this document it would be good to look at an example text-format sound set file. You can create such a file by doing the following:

- Run Sibelius 3
- Choose **Play ▶ Edit Sound Sets**
- Select **General MIDI** and click **New**
- In the **Device** tab enter the name you want (e.g. "Test Example").
- In the same tab, switch on **Save as text** near the bottom.
- Click **OK** and quit Sibelius.
- The example file will be in **C:\Program Files\Sibelius Software\Sibelius 3\Sounds** and its filename will be similar to the name you chose (e.g. **TestExample.set**).
- If you open this file in any text editor you should see a text file with curly brace **{** and the word **FileVersion** on the following line.

Sound set syntax

The sound set starts with an open brace **{** and ends with a closing brace **}**.

The body of the sound set contains the following fields within the opening and closing braces as a series of 'tree nodes', in this order:

MIDIDevice

Syntax: MIDIDevice "GM (General MIDI) "

The name of the device, e.g. 'Roland SC8820'.

If you intend your sound set to be usable on both Mac and Windows, this must be the exact name of the device as returned by FreeMIDI. If OMS uses a different name, then you will need to create a separate copy of the file with the OMS name substituted here (so that running under OMS will load this file).

FileVersion

Syntax: `FileVersion "0020000"`

Include this line and leave it unchanged. It does *not* represent the version number of the particular file on which you are working, but rather the version of the syntax used by the file, i.e. the value **0020000** corresponds with Sibelius 3, but this may change in future versions of Sibelius if the sound set format changes. (Check the sound set files supplied with future versions of Sibelius to determine if this version number has been increased.)

The version number is made of 2 parts. The upper part (which is a multiple of 10000) is the major part. The lower part (which is the remainder if you divide the whole number by 10000) is the minor part. This document describes major version 2 minor version 0, or 2.0. If a sound set for a future version of Sibelius changes the minor part only (e.g. from 2.0 to 2.1) then the current version of Sibelius will still be able to open it. If it changes the major version however (e.g. from 2.0 to 3.0) then the current version of Sibelius won't be able to open it. Future versions of Sibelius will always be able to open current versions of the sound set format (so Sibelius 3 will be able to open Sibelius 2 sound sets, even though their major version number is 1). So summarize, minor version changes are downwardly compatible, major version changes are not.

Header

Syntax: `Header`

```
{
    DefaultDevice "True"
    ProgramsCountFrom0 "False"
    Sensitivity "5"
    KontaktSet "False"
    AddOn "False"
}
```

- `DefaultDevice` – this should always be set to **False**, unless it's the **General MIDI.set** sound set file. Only one sound set file in the Sounds folder can have this parameter set to **True**; this determines which sound set is selected by default in Sibelius's **Play ▶ Devices** dialog.
- `ProgramsCountFrom0` – this value describes whether the program numbers in the sounds file are listed relative to 0 or 1. The values displayed in the Mixer window in Sibelius itself are relative to 0 or 1 depending on the setting in the Mixer's **Display** dialog.
- `Sensitivity` – a value from 1–10 inclusive which specifies a velocity curve. Each time a NoteOn message goes through a device, its velocity is mapped through this curve. Curve 5 leaves velocities unchanged. Velocity curve 1 expands velocities and curve 10 compresses them. See **Appendix C** for details of each velocity curve.
- `KontaktSet` – True if this sound set is used by the Native Instruments Kontakt Player which is shipped with Sibelius. This should be set to "False" for all but the Kontakt sound sets.
- `AddOn` - True if this is an "add-on" set. If a sound set is *not* an add-on sound set then it must contain *all* the instruments in the listed in **Appendix B** and **Appendix D** within the BestSoundsForInstruments section (see below). An add-on sound set need only contain a subset of **Appendix B** or **Appendix D**.

Controllers

Syntax: `Controllers`

```
{
    Reverb "91"
    Pan "10"
    SustainPedal "64"
    SustainOn "127"
    SustainOff "0"
}
```

You should enter the above list of MIDI controllers and their corresponding controller numbers. The names must be identical to those listed above (from the **General MIDI.set** list) – no other controllers will be recognized by Sibelius (although including them won't harm its execution). The numbers should usually also be the same, as e.g. the sustain pedal is MIDI controller 64 in practically every MIDI device. Note that `SustainOn` and `SustainOff` are not MIDI controller numbers, but rather the data byte that should be applied to the MIDI controller declared in `SustainPedal` to achieve the pedal-down and pedal-up effects.

Programs

Syntax: see below.

This contains a list of all the patches (banks and program numbers) and their names. The list can be in any order, but you might find it useful to keep it in program number order as this will simplify the construction of the **Groups** and **BestSoundsForInstruments** sections (see below). Each entry in the **Programs** list has the following structure.

```
msb/lsb/pn "patch name"
{
    ChannelMask "mask"
    NumStr      "num string"
    NoteNames
    {
        nn      "note name"
    }
}
```

Words written in italics are variables, as follows:

- *msb* is MIDI controller 0 (or bank MSB) value. It can either be empty (meaning don't send MIDI controller 0) or otherwise it must be in the range 0-127 inclusive.
Note that if empty, you should still include the slash (so you may get e.g. /23/34 "Name"). Note also that 0/ is not the same as /; if 0 is present, Sibelius will send a bank change to MSB 0; if no number is present, Sibelius will not send a bank change.
- *lsb* means MIDI controller 32 (or bank LSB), and the same conditions apply as for *msb*.
Again, if empty you should still include the slash (so you may get e.g. //34 "Name").
- *pn* is the program number. It too must be in the range 0-127 inclusive (or 1-128 if `ProgramsCountFrom0` is False) but it cannot be empty.
- *patch name* can be any text at all – it is required. This is the name that appears in the list of sounds in the Mixer.
- *mask* is a 16-bit mask, and can be any number between 0 and 65535. If you were to convert it into a binary number, each bit in that number would correspond to a MIDI channel. 1 means this sound can go on this channel, and 0 means it can't. So, say a patch could only go on channels 1, 4 and 12. Since we count MIDI channels from 0, this becomes 0, 3 and 11. With the least significant bit being the lowest channel number, this can be represented by the binary number 100000001001 and in decimal this is 2057. So for this patch, the **ChannelMask** field would take the value 2057. If you leave out the entire **ChannelMask** line, Sibelius assumes that the *mask* value is 65535 (i.e. the patch can be set on any channel). The three most common *mask* values are 65023 (all channels except channel 10), 512 (channel 10) and 65535 (all channels).
- *num string* is not currently used by Sibelius but is created by FreeMIDI and OMS. If you're creating sounds files by hand from scratch, don't bother with these fields, but if you're starting out with a FreeMIDI sounds file then you might as well leave the fields there – they do no harm.

The NoteNames list is optional. It contains the mapping from MIDI key number (or note number) and a name for that key. This is used by e.g. drum set staves, where Sibelius needs to map a MIDI key value to a note name such as "Tambourine".

- *nn* is the MIDI note number. It has to be in the range 0-127 inclusive.
- *note name* is the corresponding note name. It is essential that note names remain device-independent. For example, say MIDI device A has a drum set with a triangle sound. That sound might be called "Triangle 1". It is essential that another device MIDI device B, if it too has a triangle sounds on a drum set, that the sounds there is called "Triangle 1" too. If you were to call it "Triangle" or "triangle 1" or "Trngle" then Sibelius wouldn't know that it was the same sound. What this amounts to is that we need to agree on a common set of drum note names for all devices. A complete list is in **Appendix A**, which also specifies the General MIDI note numbers for each sound.

Groups

Syntax: see below.

This is used to organise the sounds into groups that will appear when accessing the **Sound** menu in the Mixer window (when you have the **Display sounds by type** option switched on in the Mixer's **Display** dialog). Each entry consists of a list of indexes into the **Programs** list. These indexes are relative to 0 (so the 3rd entry in the **Programs** list will be '2' in the **Groups** list). One program can appear in several groups if required. *Note: this is something that cannot be done in the Sound Set Editor in Sibelius – using the Sound Set Editor you cannot place any patch in more than one group – you can if you edit the sound set "by hand" using the information in this document.*

The **Groups** section consists of a list of lists, e.g.

```
Groups
{
    "Keyboards"
    {
        22
        1
        2
    }
    "Pitched Percussion"
    {
        114
        10
        13
    }
}
```

and so on. Each sub-list has a title enclosed in double quotes (e.g. "Pitched Percussion" above).

Note! It is essential that a patch referred to in a **Groups** sub-list actually exists. For example, say you had 128 patches in the **Programs** list. If you put the number 140 in one of the **Groups** sub-lists then Sibelius may become unstable or crash while using this sound set. More precisely, if there are N entries in the **Programs** list, then the index numbers used in the **Groups** sub-lists must be in the range 0 to $N-1$ inclusive. Indices into the **Programs** list count from 0.

You may want to copy the **Groups** section from an existing sound set file (e.g. **General MIDI.set**) and remove the lists of indices in each sub-list as a basis for your own groups.

BestSoundsForInstruments

This section is used by Sibelius to work out which program number to use to correctly play back a particular staff. With a new sound set file you may need to press the **Reset Sounds** button to set each staff to use the correct program number. This section is also used when importing a MIDI file, so that Sibelius can determine which instrument is required on each staff according to the program numbers used in the MIDI file.

It is essential that this list contain every instrument included in Sibelius. You may want to copy this section from an existing sound set file (e.g. **General MIDI.set**) as a basis for your own sound set.

A complete list of instruments is in **Appendix B**. Note that the names in this list are internal; that is, they are not necessarily as they appear in Sibelius either in the **Create Z Instruments** dialog or as instrument names in the score. Some of the names include special 'escape' characters (such as `\n` and `~`) which you should not remove, edit or change. These internal names should still be used even if your copy of Sibelius is a foreign-language version, rather than translated instrument names. As a result, sound set files are largely language-independent (apart from the names of the sounds themselves as they appear in the Mixer, which can be in any language).

Sibelius will reject any sound set file that lists any instruments that are not included in Sibelius and, conversely, it will also reject if there are instruments in Sibelius which aren't listed here (the exception to this rule is *specializations* – see below).

The syntax is as follows:

```
BestSoundsForInstruments
{
    "Bass Viol"
    {
        43
        49
    }
    "Crotales"
    {
        114
    }
}
```

and so on. Under each instrument is a list of patch indices:

- This list of indices can be empty. If you don't supply any indices, Sibelius will default to piano for this sound, or will not change the sound if it is a 'specialization'.

- The first index in the list is used when creating an instrument in Sibelius. So for example, if you create "Violin I", Sibelius will look up "Violin I" in the sounds file and use the first patch indexed under this name. The other patches indexed are used when mapping from bank/program numbers to instruments when reading MIDI files into Sibelius.
- The rules governing index ranges are exactly the same as for Groups.
- In order for Sibelius to be able to map keywords such as "pizz" and "mute" to patches in a device independent way, "instruments" are known internally by Sibelius which aren't real instruments at all. **Appendix D** lists these "instruments", which never show up in the **Create Z Instruments** dialog in Sibelius, and which represent sound effects such as pizzicato, tremolo etc. You will find these "instruments" at the end of the **BestSoundsForInstruments** section in the **General MIDI.set** file. These entries must exist in every sound set.
- You can also add in *specializations* in this section, e.g. "Mute:Trumpet". Specializations are optional and should only exist if that particular MIDI device supports that sound.

The syntax for this is "*sound-effect-instrument:real-instrument*". *sound-effect-instrument* has to be one of entries in **Appendix D**. *real-instrument* has to be a 'real' instrument in **Appendix B** (e.g. 'Violin 1' or 'Clarinet'). This is so that you can distinguish between, for instance, a muted trumpet and a muted trombone.

If Sibelius sees that you've got a keyword which maps to the Mute effect in the Trumpet staff, then it will look in the sound set file for "Mute:Trumpet" and, if it finds it, will use it. Otherwise, it will use the "Mute" entry (which must exist).

For the sound effect "Solo" and "Tutti" you should make sure that specializations should come in pairs, e.g. if you have "Solo:Flute" you must ensure you have "Tutti:Flute" otherwise Sibelius has no way of switching back and forth between the two. You'll notice that most of these sound effects are not used in the **General MIDI.set** file (i.e. they're empty) – that's because those sounds don't exist in the General MIDI sound map.

Appendix A: Drum sounds

This is a list of the General MIDI drum sounds and their corresponding MIDI note numbers:

35	Acoustic Bass Drum
36	Bass Drum 1
37	Side Stick
38	Acoustic Snare
39	Hand Clap
40	Electric Snare
41	Low Floor TomTom
42	Closed Hi-Hat
43	High Floor TomTom
44	Pedal Hi-Hat
45	Low TomTom
46	Open Hi-Hat
47	Low-Mid TomTom
48	Hi-Mid TomTom
49	Crash Cymbal 1
50	High TomTom
51	Ride Cymbal 1
52	Chinese Cymbal
53	Ride Bell
54	Tambourine
55	Splash Cymbal
56	Cowbell
57	Crash Cymbal 2
58	Vibraslap
59	Ride Cymbal 2
60	Hi Bongo
61	Low Bongo
62	Mute Hi Conga
63	Open Hi Conga
64	Low Conga
65	High Timbale
66	Low Timbale
67	High Agogo
68	Low Agogo
69	Cabasa
70	Maracas
71	Short Whistle
72	Long Whistle
73	Short Guiro
74	Long Guiro
75	Claves
76	Hi Wood Block
77	Low Wood Block
78	Mute Cuica
79	Open Cuica
80	Mute Triangle
81	Open Triangle

Appendix B: Complete list of instruments

Piccolo
E~b Flute
Flute
Shakuhachi
Alto Flute
Bass Flute
Sopranino Recorder
Soprano Recorder
Descant Recorder
Alto Recorder
Treble Recorder
Tenor Recorder
Bass Recorder
Great Bass Recorder
Contrabass Recorder
Tin Whistle
Flageolet
Ocarina
Panpipes
Oboe
Oboe d'amore
Cor Anglais
English Horn
Baritone Oboe
Bass Oboe
Heckelphone
Clarinet in E~b
Clarinet in D
Clarinet in C
Clarinet in B~b
Clarinet in A
Clarinet in A~b
Alto Clarinet in E~b
Alto Clarinet in E~b [bass clef]
Basset-horn
Bass Clarinet\n\nin B~b
Bass Clarinet [bass clef]
Contra Alto\n\nClarinet in E~b
Contra Alto\n\nClarinet in E~b [bass clef]
Contrabass\n\nClarinet in B~b
Contrabass\n\nClarinet in B~b [bass clef]
Contrabass\n\nClarinet in E~b
Contrabass\n\nClarinet in E~b [bass clef]
Sopranino\n\nSaxophone in B~b
Sopranino\n\nSaxophone
Soprano Saxophone
Alto Saxophone
Tenor Saxophone
Tenor Saxophone [bass clef]
Baritone Saxophone
Baritone Saxophone [bass clef]
Bass Saxophone
Bass Saxophone [bass clef]
Contrabass Saxophone in Bb
Contrabass Saxophone in Bb [bass clef]
Contrabass Saxophone
Contrabass Saxophone [bass clef]
Quart Bassoon
Quint Bassoon
Bassoon

Contrabassoon
Harmonica
Bagpipe
Didgeridoo
Woodwind
Horn in B~b [no key]
Horn in A [no key]
Horn in A~b alto [no key]
Horn in G [no key]
Horn in F~# [no key]
Horn in F
Horn in F [bass clef]
Horn in F [no key]
Horn in E [no key]
Horn in E~b [no key]
Horn in D [no key]
Horn in D~b [no key]
Horn in C [no key]
Horn in B [no key]
C Basso Horn [no key]
B~b Basso Horn [no key]
A Basso Horn [no key]
Wagner Tuba in B~b
Wagner Tuba in F
Tenor Tuba
Alp-Horn in G
Alp-Horn in F
Alto Horn in F
Alto Horn in E~b
Mellophone in F
Mellophone in E~b
Mellophonium in F
Mellophonium in E~b
Soprano Bugle in G
Mellophone Bugle in G
Baritone Bugle in G
Euphonium Bugle in G
Contrabass Bugle in G
Piccolo Trumpet in B~b
Piccolo Trumpet in A
Trumpet in G [no key]
Trumpet in E [no key]
Trumpet in E~b
Trumpet in D
Trumpet in D~b
Trumpet in C
Trumpet in B [no key]
Trumpet in B~b
Trumpet in B~b [no key]
Trumpet in A
Trumpet in F
Tenor Trumpet in E~b
Bass Trumpet in E~b
Bass Trumpet in B~b
Bass Trumpet in D
Soprano Cornet E~b
Cornet in B~b
Cornet in A
Flugelhorn
Tenor Horn
Trombone [treble clef]
Trombone
Trombone [bass clef, treble in parts]

Alto Trombone
Tenor Trombone
Bass Trombone
Contrabass Trombone
Euphonium
Euphonium [bass clef]
Euphonium [bass clef always]
Baritone
Baritone Horn
Baritone Horn [bass clef]
Baritone Horn [bass clef always]
Tuba
Tuba in F
Sousaphone in B~b
Sousaphone in E~b
Ophicleide
Serpent
Bass in B~b
Bass in B~b [bass clef]
Bass in E~b
Bass in E~b [bass clef]
Cimbasso in F
Cimbasso in E~b
Cimbasso in B~b
Brass
Brass [treble staff]
Cornet
Solo Cornet B~b
Repiano Cornet B~b
2nd Cornet B~b
3rd Cornet B~b
Solo Horn E~b
1st Horn E~b
2nd Horn E~b
1st Baritone B~b
2nd Baritone B~b
1st Trombone B~b
2nd Trombone B~b
Euphonium B~b
Timpani [no key]
Timpani [with key]
Drums
Drums [drum set]
Drum Kit
Drum Set
Percussion [1 line]
Percussion [2 lines]
Percussion [3 lines]
Percussion [4 lines]
Percussion [5 lines]
Anvil
Bass drum
Bass drum [5 lines]
Marching Bass Drum [3 lines]
Marching Bass Drum [5 lines]
Bongo
Castanets
Conga
Cymbals
Roto-toms
Side drum
Snare drum
Snare drum [5 lines]

Sleigh bells
Taiko Drum
Tambourine
Tam-tam
Temple blocks
Tenor drum
Tom-toms
Quads [tom-toms]
Triangle
Whistle
Whip
Wood blocks
Almglocken
Antique Cymbals
Crotales
Cimbalom
Dulcimer
Dulcimer [notation]
Dulcimer (DAA tuning) [tab]
Dulcimer (DAD tuning) [tab]
Zither
Handbells
Tubular bells
Chimes
Chimes [no key]
Gong
Steel drums
Steel drums [bass clef]
Glockenspiel
Bells [marching band]
Orchestral Bells
Xylophone
Xylorimba
Marimba [treble staff]
Marimba [grand staff]
Vibraphone
Harp
Troubadour Harp
Guitar
Guitar [tab]
Classical Gtr [notation]
Classical Gtr Standard tuning [tab]
Classical Gtr Standard tuning (no rhythms) [tab]
Classical Gtr Dropped D tuning [tab]
Classical Gtr Double D tuning [tab]
Classical Gtr Open G tuning [tab]
Classical Gtr Open D tuning [tab]
Classical Gtr Open E tuning [tab]
Classical Gtr DADGAD tuning [tab]
12-string Guitar
12-string Guitar [tab]
12-string Gtr [notation]
12-string Gtr Standard tuning [tab]
12-string Gtr Standard tuning (no rhythms) [tab]
12-string Gtr Dropped D tuning [tab]
12-string Gtr Double D tuning [tab]
12-string Gtr Open G tuning [tab]
12-string Gtr Open D tuning [tab]
12-string Gtr Open E tuning [tab]
12-string Gtr DADGAD tuning [tab]
Acoustic Guitar
Acoustic Guitar [tab]
12-string Acoustic Guitar

12-string Acoustic Guitar [tab]
 Acoustic Gtr [notation]
 Acoustic Gtr Standard tuning [tab]
 Acoustic Gtr Standard tuning (no rhythms) [tab]
 Acoustic Gtr Dropped D tuning [tab]
 Acoustic Gtr Double D tuning [tab]
 Acoustic Gtr Open G tuning [tab]
 Acoustic Gtr Open D tuning [tab]
 Acoustic Gtr Open E tuning [tab]
 Acoustic Gtr DADGAD tuning [tab]
 Semi-acoustic Gtr [notation]
 Semi-acoustic Gtr Standard tuning [tab]
 Semi-acoustic Gtr Standard tuning (no rhythms) [tab]
 Semi-acoustic Gtr Dropped D tuning [tab]
 Semi-acoustic Gtr Double D tuning [tab]
 Semi-acoustic Gtr Open G tuning [tab]
 Semi-acoustic Gtr Open D tuning [tab]
 Semi-acoustic Gtr Open E tuning [tab]
 Semi-acoustic Gtr DADGAD tuning [tab]
 Electric guitar
 Electric guitar [tab]
 Electric Gtr [notation]
 Electric Gtr Standard tuning [tab]
 Electric Gtr Standard tuning (no rhythms) [tab]
 Electric Gtr Dropped D tuning [tab]
 Electric Gtr Double D tuning [tab]
 Electric Gtr Open G tuning [tab]
 Electric Gtr Open D tuning [tab]
 Electric Gtr Open E tuning [tab]
 Electric Gtr DADGAD tuning [tab]
 Electric guitar (distortion) [notation]
 Electric guitar (distortion) [tab]
 7-string Electric guitar
 12-string Electric guitar
 12-string Electric guitar [tab]
 Acoustic Bass
 Acoustic Bass [tab]
 Bass guitar
 Bass guitar [tab]
 4-string Bass Guitar
 4-string Bass Guitar [tab]
 5-string Bass Guitar
 5-string Bass Guitar [tab]
 6-string Bass Guitar
 6-string Bass Guitar [tab]
 Fretless Bass Guitar
 Fretless Bass Guitar [notation]
 Fretless Bass guitar [tab]
 5-string Fretless Bass Guitar
 5-string Fretless Bass Guitar [tab]
 6-string Fretless Bass Guitar
 6-string Fretless Bass Guitar [tab]
 Electric Bass
 Electric Bass [tab]
 5-string Electric Bass
 5-string Electric Bass [tab]
 6-string Electric Bass
 6-string Electric Bass [tab]
 Fretless Electric Bass
 Fretless Electric Bass [tab]
 5-string Fretless Electric Bass
 5-string Fretless Electric Bass [tab]
 6-string Fretless Electric Bass

6-string Fretless Electric Bass [tab]
Banjo
Banjo [tab]
Banjo [Standard C]
Banjo [Standard C tab]
Banjo [G tuning]
Banjo [G tuning tab]
Banjo [Two C tuning]
Banjo [Two C tuning tab]
Banjo [G modal]
Banjo [G modal tab]
Banjo [D tuning]
Banjo [D tuning tab]
Banjo [notation]
Banjo (gDGBD tuning) [tab]
Banjo (gDGCD tuning) [tab]
Banjo (gCGCD tuning) [tab]
Banjo (aEADE tuning) [tab]
Banjo (eDADE tuning) [tab]
Tenor Banjo [notation]
Tenor Banjo
Tenor Banjo [tab]
Pedal Steel Guitar
Pedal Steel Guitar [tab]
Hawaiian Steel Guitar
Hawaiian Steel Guitar [tab]
6-string Hawaiian Steel Guitar [tab]
8-string Hawaiian Steel Guitar [tab]
10-string Hawaiian Steel Guitar [tab]
Lute
Lute [tablature]
Lute [notation]
Lute (tenor G tuning) [tab]
Lute (treble tuning) [notation]
Lute (treble tuning) [tab]
Lute (bass D tuning) [notation]
Lute (bass D tuning) [tab]
Mandolin
Mandolin [notation]
Mandolin [tab]
Gamba [notation]
Gamba [tab]
Requinto [notation]
Requinto [tab]
Vihuela [notation]
Vihuela [tab]
Dobro [notation]
Dobro [tab]
Ukulele
Ukulele [tab]
Koto
Shamisen
Sitar
Sitar [notation]
Sitar (Ravi Shankar) [tab]
Sitar (Vilayat Khan) [tab]
Voice
Vocals
Backing vocals
Treble
Mean
Cantus
Soprano

Mezzo-soprano
Secundus
Contralto
Alto
Altus
Counter-tenor
Tenor
Quintus
Baritone
Bass
Bassus
Choir
Celesta
Piano
Honky-tonk piano
Electric Piano
Keyboard
Keyboards
Synthesizer
Clavichord
Harpsichord
Organ [manuals]
Ped. [organ pedals]
Manuals [solo organ manuals]
Pedal [solo organ pedals]
Electric Organ
Ondes Martenot
Accordion
Harmonium
Melodeon
Violin
Violin 1
Violin 2
Violin I
Violin II
Viola
Violoncello
Contrabass
Double bass
String Bass
Treble Viol
Tenor Viol
Bass Viol
Hurdy-gurdy
Strings
Strings [reduction]
Strings [treble staff]
Piano [chamber music]
Solo [treble staff]
 [treble staff]
 [bass staff]
 [small staff]
Tape
Sampler
Theremin
Applause
Birdsong
Helicopter
Seashore
Telephone


```
80,81,81,82,83,83,84,84,85,86,86,87,87,88,89,89,90,90,91,92,
92,93,94,94,95,95,96,97,97,98,98,99,100,100,101,101,102,103,104,
104,105,105,106,106,107,107,108,108,109,109,110,110,111,111,111,112,112,113,
113,113,113,114,114,114,115,115};
static Byte g_VelocityCurve10[128] = {
0,50,51,52,52,53,54,55,56,57,58,58,59,60,61,62,63,63,64,65,
66,67,67,68,68,69,70,70,71,71,72,72,73,74,74,75,75,76,77,77,
78,78,79,79,80,81,81,82,82,83,83,84,85,85,86,86,87,88,88,89,
89,90,90,91,92,92,93,93,94,94,95,95,96,96,97,97,98,98,99,99,
100,100,101,101,102,102,103,103,104,104,105,105,105,106,106,107,107,108,108,108,
109,109,110,110,110,111,111,112,112,113,113,113,114,114,115,115,116,116,116,
116,117,117,117,117,118,118,118};
```

Appendix D: Effects Instruments

Solo (real)
Pizzicato
Mute
Tremolo
Spiccato
Col Legno
Detaché
Legato
Harmonics
Snap Pizzicato
Sul Ponticello
Sul Tasto
Open
Closed
Solo
Tutti